Handling Vault Node Restart

Each time a Vault node restarts, you will have to unseal it, so that it can participate in the cluster. Here are steps to do that.

Switch to root on the node with:

```
sudo -i
```

Set exports for the node:

> NOTE: Make sure that the vault_addr variable is pointing to the local node being unsealed, here.

```
export VAULT_ADDR="https://vault0205.ogsofttech.lan:8200";
export VAULT_CACERT="/opt/vault/tls/ca.crt"
```

> NOTE: Use the fully-qualified hostname above, as it appears in the node's cert.

Now, unseal each node, by calling this command once each, for three of the five unseal keys:

> NOTE: It will prompt you for the unseal key, each time you run it.

```
vault operator unseal
```

Once unsealed, you can verify cluster membership with this:

```
vault operator raft list-peers
```

When run, you will see something like this:

```
root@vault0204:~# vault operator raft list-peers
Node          Address                State       Voter
----          -------                -----       -----
vault0204     192.168.75.24:8201     leader      true
vault0205     192.168.75.25:8201     follower    true
vault0206     192.168.75.26:8201     follower    true
root@vault0204:~#
```

If healthy, you will see one node as leader, and the others as voting followers.

> NOTE: Make sure each node you configured, is present.

Revision #2
Created 4 September 2025 04:56:01 by glwhite
Updated 4 September 2025 05:03:21 by glwhite